CA400 Final Year Computer Applications Project

Document Type: User Manual



Project Title: Human Activity Recognition using wrist-mounted sensors based on Symbolic

Aggregate Approximation and Machine Vision

Student: Shane Creedon

Student ID: 15337356

Supervisor: Tomas Ward

Date of Completion: 17/05/2019

1 Abstract

This document is the user manual behind my fourth year project based on Human Activity Recognition. In this document I will provide a step-by-step approach involving how to setup, start, and utilise the application. For my particular software project, I have it split up into two components:

- 1. The Web Application
- 2. The Desktop Application

For each section in this user manual, insight and guidance for both of the above listed components will be discussed and mentioned. This document will also contain screenshots to help further with this process of comprehension.

2 Installation

Before I specify instructions relating to both components of my project, I want to provide some pre-initialization steps:

- 1. Clone repository from Gitlab.
- 2. Install all requirements in requirements.txt file (pip install -r requirements.txt)
- 3. It is generally a good idea to set up a Python Virtual Environment prior to installing all requirements. (virtualenv {environment_name}

Web Application Component:

Once all the requirement packages are installed using the above steps, running the web application becomes quite easy.

- 1. Navigate to src/code/website_module/website-implementation/
- 2. Run: 'python manage.py runserver'

The script should initialise the web application on port 8000. Simply open up your browser and enter: localhost:8000 or 127.0.0.1:8000 and you will see the web application i've built.

Alternatively, I am hosting the website online using Nginx and Gunicorn and can be viewed here: https://www.projectactivityrecognition.ml

Desktop Application Component

Similarly to the above component, it is essential all requirements are downloaded prior to using the application. Again, generally it is advised to use a virtual environment in these scenarios to prevent version conflicts with packages. It is required you spin up a client and server instance to run the desktop software sufficiently and I will detail both procedures below.

NB: It is essentially important that you install a piece of broker software to facilitate the MQTT protocol. To do

this, navigate to https://mosquitto.org/ and download the mosquitto broker software on your desired operating system. By default once downloaded, the broker should be an active background process on your machine and will be accessible at 127.0.0.1:1883. This step is crucial before testing out the desktop software. Both files will be runnable without this broker active, but the implemented functionality will not work.

Server:

- Navigate to src/code/mgtt protocol module/
- 2. Run: 'python server_connect.py'

The server should spin up and subscribe to various topics. Once this happens, you know the server is successfully active.

Client:

- 1. Navigate to src/code/desktop_gui_module/main/
- 2. Run: 'python application.py'

The client application should spin up and appear as an application on your screen.

3 User Guide


Website Instructions:

To successfully use the website, either access it using the above **installation** methods or as previously mentioned, access the website at: https://www.projectactivityrecognition.ml.

Once you arrive at the website you will arrive at the homepage where you can interact with several key components/features on the website.

Home:

The **Download** functionality which is accessible through clicking the white button labeled 'download'.
 A zip file contained the client-side software as well as instructions on how to use it will be downloaded upon click. This is available at the top of the home page.




2. The **Developer** section, where by users can read a bit about me and why I wanted to get involved in data science and human activity recognition. This section is available at the bottom of the home page.




Research

1. The research section simply offers information on the different aspects and techniques I utilised to build my project. Once the tab is clicked, the page will load up in a grid pattern with each technique corresponding to a grid item. I also provide links for further information about any techniques used.




Blog

1. The blog also offers no real interaction other than researching and understanding about how the project works as well as the process that was undertaken to create it. I have over 35 blog entries describing the process from start to finish and also providing details about how someone can use the knowledge i've gained in their own projects / technical ventures. Simply scroll up and down to read about my project milestones with insightful images to aid.



Discussion

- 1. The discussion section is dramatically more interactive offering the ability for users to join in on a discussion with other users in relation to human activity recognition. Users will be able to view other users comments, with each comment containing a particular author, comment date, comment text and comment time.
- 2. Users can join the discussion by entering a form name into the name box below and also provide relative comment text. Clicking the submit button will post their comment up for all to see.



Desktop Application Instructions:

Open the desktop application using the above installation instructions, spin up both the server application and the client application, in that order. Users should subsequently be greeted with the desktop application overview screen.

Overview:

- 1. The overview window is split into 4 sub window panes which act as summarizations of the 4 tab choices at the top of the application frame. Users can only interact with the bottom-left pane which is denoted as the 'controller' pane, since it controls the other window panes.
- 2. Users will notice two flashing red or green icons at the bottom of the desktop software which are indicative of whether the client is successfully connected to the broker and whether the client has a successful PPG connection.
 - Note: If you have an arduino PPG connected and this icon has not changed to green, you may need to find out what port the arduino is connected on and set the application to that port. This can be done in the port settings in the menu bar at the top of the software.
 - Once the Arduino PPG is connected, you should see the top-left pane (Graph Pane) start picking up your heart-rate and motion artefacts from any inertial movements.
- 3. Users can select the visibly green button in the controller pane (bottom-left) to activate activity recognition playback. This function when clicked will bring up a file explorer dialog box, where by users can select any PPG recording files in the form of a csv. It is essential there is an active server to facilitate this request, so if you receive no feedback it is likely the server is not available or is not online.
 - Users will notice a loading icon appear and the loading bar appear start to progress in relation to the length of the csv file submitted. After several seconds of waiting, (3-4 seconds) the server will start responding to the client with what activity it thinks the client submitted. The server will go through the submitted csv file and adequately "guess" what it thinks activity had been performed.
 - Users will notice the UI update to reflect what activity the server believes is being performed. The UI avatar (mario) will update to reflect the 4 cardinal activities of Walking, Running, Slow Cycle and Fast Cycle respectively. Additionally, users can view the time of the activity as well as the predictive accuracy. The graph view pane (Top-Right) will also update to show the PPG recording signal at that particular moment in time.
- 4. When the previous step is activated, all the buttons in the controller pane will be 'greyed out' indicating they cannot be clicked. This is the case for all buttons except for one labeled 'cancel activity playback'. This button can be clicked by users to cancel an in-progress playback function. This is crucial to end the process early and try out other aspects of the application.
- 5. Once there is an active arduino PPG connected to the correct port, users can record that activate connection using the 'Recording Mode' button available in the controller pane. This will take the microvolt signal generated and record it into a csv file, specifically labeled: 'voltages01/02/03.csv' etc. The more recordings the user takes, the higher the increment. Such that files will not be overwritten. This file will be stored in the downloads section of a users file structure.
- 6. With an actively connected arduino PPG device, users can check what activity they are doing in real-time. This feature is only working to a degree and still has problems that need to be ironed out.

7. Users can read the research on the project and learn more about the inspirations from where it came.

🔇 Arduino Software - Human Activity Recognition via PPG sensor File Settings Help Overview Activity Recognition View Real-Time Graph View 1850 1800 1750 1700 1650 1600 Activity Recognition Playback Project Research Areas Follow my Progress: - https://www.projectactivityrecognition.ml/blog What is Human Activity Recognition? http://doras.dcu.ie/22433/ What is Symbolic Aggregate Approximation? - http://doras.dcu.ie/22433/ What are Convolutional Neural Networks? - http://doras.dcu.ie/22433/ Cancel Recognition Playback What is Transfer Learning? - http://doras.dcu.ie/22433/ Developed By: Shane Creedon (https://www.skybreak.cf) Supervised By: Tomas Ward (https://www.insight-centre.org/users/tomas-ward) Arduino PPG Not Connected

Fig 3.0 - Desktop Application Overview Screen

Menu Bar Features:

Users can utilise the menu bar for several different purposes:

1. File

Under the file menu item, there exist the options for 'settings', 'about' and 'exit' each of which should be intuitive for a user to comprehend by naming convention alone. 'Settings' holds the ability to update the port for the arduino connection. Clicking 'About' will pop up another window explaining the mission behind the application in-depth. 'Exit' as the name suggest will close the application.

2. Settings

Under the settings menu item, there exists the option for 'port' which provides the same functionality as 'settings' under the file menu. Again, this is just for usability and ease of access of features.

3. Help

Under the help menu item, there exists the option for 'application guide' which as the name suggests provides a pop-up window with instructions and intricacies about using the application successfully.

Fig 3.1 - Menu Bar Items & Tab Items

